



w: www.mariadb.com

e: info@mariadb.com

MaxAdmin

The MariaDB MaxScale Administrative & Monitoring Client Application

Mark Riddoch

Last Updated: 19th November 2014



w: www.mariadb.com

e: info@mariadb.com

Contents

Overview.....	4
Running MaxAdmin.....	4
Command Line Switches	4
Interactive Operation	5
Command Line Operation.....	5
Getting Help	8
Working With Services	10
What Services Are Available?	10
See Service Details	11
Examining Service Users.....	11
Reloading Service User Data	12
Stopping A Service	12
Restart A Stopped Service	12
Working With Servers	13
What Servers Are Configured?	13
Server Details.....	13
Setting The State Of A Server	14
Working With Sessions	15
What Sessions Are Active in MaxScale?	15
Display Session Details	16
Descriptor Control Blocks.....	17
Finding DCB's	17
DCB Of A Client Connection.....	18
DCB Details.....	18
Working with Filters.....	19
What Filters Are Configured?	19
Retrieve Details Of A Filter Configuration	19



w: www.mariadb.com

e: info@mariadb.com

Filter Usage	20
Working With Monitors	23
What Monitors Are Running?	23
Details Of A Particular Monitor	23
Controlling Replication Heartbeat	23
Shutting Down A Monitor	24
Restarting A Monitor	25
Working With Administration Interface Users	26
What Users Have Been Defined?	26
Add A New User	26
Delete A User	27
MaxScale Status Commands	28
MaxScale Thread Usage	28
The Event Queue	28
The Housekeeper Tasks	29
Administration Commands	29
What Modules Are In use?	29
Rotating the log files	30
Change MaxScale Logging Options	30
Reloading The Configuration	30
Shutting Down MaxScale	31
Configuring MaxScale to Accept MaxAdmin Connections	32
Tuning MaxScale	32



w: www.mariadb.com

e: info@mariadb.com

Overview

MaxAdmin is a simple client interface that can be used to interact with the MaxScale server, it allows the display of internal MaxScale statistics, status and control of MaxScale operations.

MaxAdmin supports

- Interactive user sessions
- Execution of one-off commands via command line arguments
- Execution of command scripts

Running MaxAdmin

The MaxAdmin client application may be run in two different modes, either as an interactive command shell for executing commands against MaxScale or by passing commands on the MaxAdmin command line itself.

Command Line Switches

The MaxAdmin command accepts a number of switches

Switch	Long Option	Description
-u user	--user=...	Sets the username that will be used for the MaxScale connection. If no -u option is passed on the MaxAdmin command line then the default username of 'admin' will be used.
-p password	--password=...	Sets the user password that will be used. If no -p option is passed on the command line then MaxAdmin will prompt for interactive entry of the password.
-h hostname	--hostname=...	The hostname of the MaxScale server to connect to. If no -h option is passed on the command line then MaxAdmin will attempt to connect to the host 'localhost'.
-P port	--port=...	The port that MaxAdmin will use to connect to the MaxScale server. if no -P option is given then the default port of 6603 will be used.
-?	--help	Print usage information regarding MaxAdmin



w: www.mariadb.com

e: info@mariadb.com

-v	--version	Print the maxadmin version information and exit
----	-----------	---

When a switch takes a value, this may either be as the next argument on the command line or maybe as part of the switch itself. E.g. `-u me` and `-ume` are treated in the same way.

Interactive Operation

If no arguments other than the command line switches are passed to MaxAdmin it will enter its interactive mode of operation. Users will be prompted to enter commands with a **MaxScale>** prompt. The commands themselves are documented in the sections later in this document. A help system is available that will give some minimal details of the commands available.

Command history is available on platforms that support the libedit library. This allows the use of the up and down arrow keys to recall previous commands that have been executed by MaxAdmin. The default edit mode for the history is to emulate the vi commands, the behaviour of libedit may however be customised using the `.editrc` file. To obtain the history of commands that have been executed use the inbuilt `history` command.

In interactive mode it is possible to execute a set of commands stored in an external file by using the `source` command. The command takes the argument of a filename which should contain a set of MaxScale commands, one per line. These will be executed in the order they appear in the file.

Command Line Operation

MaxAdmin can also be used to execute commands that are passed on the command line, e.g.

```
-bash-4.1$ maxadmin -hmaxscale list services
Password:
Services.
-----+-----+-----+-----
Service Name      | Router Module      | #Users | Total Sessions
-----+-----+-----+-----
Test Service      | readconnroute      | 1      | 1
Split Service     | readwritesplit      | 1      | 1
Filter Service    | readconnroute      | 1      | 1
QLA Service       | readconnroute      | 1      | 1
Debug Service     | debugcli            | 1      | 1
CLI               | cli                 | 2      | 27
-----+-----+-----+-----

-bash-4.1$
```



w: www.mariadb.com

e: info@mariadb.com

The single command is executed and MaxAdmin then terminates. If the -p option is not given then MaxAdmin will prompt for a password. If a MaxScale command requires an argument which contains whitespace, for example a service name, that name should be quoted. The quotes will be preserved and used in the execution of the MaxScale command.

```
-bash-4.1$ maxadmin show service "QLA Service"
Password:
Service 0x70c6a0
  Service:          QLA Service
  Router:           readconnroute (0x7ffff0f7ae60)
  Number of router sessions:      0
  Current no. of router sessions: 0
  Number of queries forwarded:    0
  Started:           Wed Jun 25 10:08:23 2014
  Backend databases
    127.0.0.1:3309 Protocol: MySQLBackend
    127.0.0.1:3308 Protocol: MySQLBackend
    127.0.0.1:3307 Protocol: MySQLBackend
    127.0.0.1:3306 Protocol: MySQLBackend
  Users data:       0x724340
  Total connections: 1
  Currently connected: 1
-bash-4.1$
```

Command files may be executed by either calling MaxAdmin with the name of the file that contains the commands

```
maxadmin listall.ms
```

Or by using the #! mechanism to make the command file executable from the shell. To do this add a line at the start of your command file that contains the #! directive with the path of the MaxAdmin executable. Command options may also be given in this line. For example to create a script file that runs a set of list commands

```
#!/usr/local/bin/maxadmin -hmaxscalehost
list modules
list servers
list services
list listeners
list dcbs
list sessions
list filters
```



w: www.mariadb.com

e: info@mariadb.com

Then simply set this file to have execute permissions and it may be run like any other command in the Linux shell.



w: www.mariadb.com

e: info@mariadb.com

Getting Help

A help system is available that describes the commands available via the administration interface. To obtain a list of all commands available simply type the command `help`.

```
MaxScale> help
Available commands:
  add user
  clear server
  disable [heartbeat|log|root]
  enable [heartbeat|log|root]
  list
[clients|dcbs|filters|listeners|modules|monitors|services|servers|sessions]
  reload [config|dbusers]
  remove user
  restart [monitor|service]
  set server
  show
[dcbs|dcb|dbusers|epoll|filter|filters|modules|monitor|monitors|server|servers|
services|service|session|sessions|users]
  shutdown [maxscale|monitor|service]
```

Type `help` command to see details of each command.

Where commands require names as arguments and these names contain whitespace either the `\` character may be used to escape the whitespace or the name may be enclosed in double quotes `"`.

```
MaxScale>
```

To see more detail on a particular command, and a list of the sub commands of the command, type `help` followed by the command name.

```
MaxScale> help list
Available options to the list command:
  clients      List all the client connections to MaxScale
  dcbs         List all the DCBs active within MaxScale
  filters      List all the filters defined within MaxScale
  listeners    List all the listeners defined within MaxScale
  modules      List all currently loaded modules
  monitors     List all monitors
  services     List all the services defined within MaxScale
  servers      List all the servers defined within MaxScale
```




w: www.mariadb.com

e: info@mariadb.com

```
    sessions  List all the active sessions within MaxScale  
MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

Working With Services

A service is a very important concept in MaxScale as it defines the mechanism by which clients interact with MaxScale and can be attached to the backend databases. A number of commands exist that allow interaction with the services.

What Services Are Available?

The `list services` command can be used to discover what services are currently available within your MaxScale configuration.

```
MaxScale> list services
Services.
-----+-----+-----+-----
Service Name      | Router Module      | #Users | Total Sessions
-----+-----+-----+-----
Test Service      | readconroute       | 1      | 1
Split Service     | readwritesplit     | 1      | 1
Filter Service    | readconroute       | 1      | 1
QLA Service       | readconroute       | 1      | 1
Debug Service     | debugcli           | 1      | 1
CLI               | cli                | 2      | 24
-----+-----+-----+-----

MaxScale>
```

In order to determine which ports services are using then the `list listeners` command can be used.

```
MaxScale> list listeners
Listeners.
-----+-----+-----+-----+-----
Service Name      | Protocol Module    | Address      | Port  | State
-----+-----+-----+-----+-----
Test Service      | MySQLClient        | *            | 4006  | Running
Split Service     | MySQLClient        | *            | 4007  | Running
Filter Service    | MySQLClient        | *            | 4008  | Running
QLA Service       | MySQLClient        | *            | 4009  | Running
Debug Service     | telnetd            | localhost    | 4242  | Running
CLI               | maxscaled          | localhost    | 6603  | Running
-----+-----+-----+-----+-----

MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

See Service Details

It is possible to see the details of an individual service using the `show service` command. This command should be passed the name of the service you wish to examine as an argument. Where a service name contains spaces characters there should either be escaped or the name placed in quotes.

```
MaxScale> show service "QLA Service"
Service 0x70c6a0
  Service:          QLA Service
  Router:           readconnroute (0x7ffff0f7ae60)
  Number of router sessions: 0
  Current no. of router sessions: 0
  Number of queries forwarded: 0
  Started:          Wed Jun 25 10:08:23 2014
  Backend databases
    127.0.0.1:3309 Protocol: MySQLBackend
    127.0.0.1:3308 Protocol: MySQLBackend
    127.0.0.1:3307 Protocol: MySQLBackend
    127.0.0.1:3306 Protocol: MySQLBackend
  Users data:       0x724340
  Total connections: 1
  Currently connected: 1
MaxScale>
```

This allows the set of backend servers defined by the service to be seen along with the service statistics and other information.

Examining Service Users

MaxScale provides an authentication model by which the client application authenticates with MaxScale using the credentials they would normally use to with the database itself. MaxScale loads the user data from one of the backend databases defined for the service. The `show dbusers` command can be used to examine the user data held by MaxScale.

```
MaxScale> show dbusers "Filter Service"
Users table data
Hashtable: 0x723e50, size 52
  No. of entries:      48
  Average chain length: 0.9
  Longest chain length: 5
User names: pappo@%, rana@%, new_control@%, new_nuovo@%, uno@192.168.56.1,
nuovo@192.168.56.1, pesce@%, tryme@192.168.1.199, repluser@%, seven@%, due@%,
pippo@%, mmm@%, daka@127.0.0.1, timour@%, ivan@%, prova@%, changeme@127.0.0.1,
uno@%, massimiliano@127.0.0.1, massim@127.0.0.1, massi@127.0.0.1,
```



w: www.mariadb.com

e: info@mariadb.com

```
masssi@127.0.0.1, pappo@127.0.0.1, rana@127.0.0.1, newadded@127.0.0.1,
newaded@127.0.0.1, pesce@127.0.0.1, repluser@127.0.0.1, seven@127.0.0.1,
pippo@127.0.0.1, due@127.0.0.1, nopwd@127.0.0.1, timour@127.0.0.1,
controlla@192.168.56.1, ivan@127.0.0.1, ppp@127.0.0.1, daka@%, nuovo@127.0.0.1,
uno@127.0.0.1, repluser@192.168.56.1, havoc@%, tekka@192.168.1.19,
due@192.168.56.1, qwerty@127.0.0.1, massimiliano@%, massi@%, massim@%
MaxScale>
```

Reloading Service User Data

MaxScale will automatically reload user data if there are failed authentication requests from client applications. This reloading is rate limited and triggered by missing entries in the MaxScale table. If a user is removed from the backend database user table it will not trigger removal from the MaxScale internal table. The `reload dbusers` command can be used to force the reloading of the user table within MaxScale.

```
MaxScale> reload dbusers "Split Service"
Loaded 34 database users for service Split Service.
MaxScale>
```

Stopping A Service

It is possible to stop a service from accepting new connections by using the `shutdown service` command. This will not affect the connections that are already in place for a service, but will stop any new connections from being accepted.

```
MaxScale> shutdown service "Split Service"
MaxScale>
```

Restart A Stopped Service

A stopped service may be restarted by using the `restart service` command.

```
MaxScale> restart service "Split Service"
MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

Working With Servers

The server represents each of the instances of MySQL or MariaDB that a service may use.

What Servers Are Configured?

The command `list servers` can be used to display a list of all the servers configured within MaxScale.

```
MaxScale> list servers
Servers.
-----+-----+-----+-----+-----
--
Server          | Address      | Port | Status          |
Connections
-----+-----+-----+-----+-----
--
server1         | 127.0.0.1    | 3306 | Running         | 0
server2         | 127.0.0.1    | 3307 | Master, Running | 0
server3         | 127.0.0.1    | 3308 | Running         | 0
server4         | 127.0.0.1    | 3309 | Slave, Running  | 0
-----+-----+-----+-----+-----
--

MaxScale>
```

Server Details

It is possible to see more details regarding a given server using the `show server` command.

```
MaxScale> show server server2
Server 0x70d460 (server2)
  Server:          127.0.0.1
  Status:          Master, Running
  Protocol:        MySQLBackend
  Port:            3307
  Server Version:  5.5.25-MariaDB-log
  Node Id:         124
  Number of connections: 0
  Current no. of conns: 0
MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

Setting The State Of A Server

MaxScale maintains a number of status bits for each server that is configured, these status bits are normally maintained by the monitors, there are two commands in the user interface that are used to manually maintain these bits also; the `set server` and `clear server` commands.

The status bit that can be controlled are

Bit Name	Description
running	The server is responding to requests, accepting connections and executing database commands
master	The server is a master in a replication setup or should be considered as a destination for database updates.
slave	The server is a replication slave or is considered as a read only database.
synced	The server is a fully fledged member of a Galera cluster
maintenance	The server is in maintenance mode. In this mode no new connections will be established to the server. The monitors will also not monitor servers that are in maintenance mode.

All status bits, with the exception of the maintenance bit, will be set by the monitors that are monitoring the server. If manual control is required the monitor should be stopped.

```
MaxScale> set server server3 maintenance
MaxScale> clear server server3 maintenance
MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

Working With Sessions

The MaxScale session represents the state within MaxScale. Sessions are dynamic entities and not named in the configuration file, this means that sessions can not be easily named within the user interface. The sessions are referenced using ID values, these are actually memory address, however the important thing is that no two session have the same ID.

What Sessions Are Active in MaxScale?

There are a number of ways to find out what sessions are active, the most comprehensive being the `list sessions` command.

```
MaxScale> list sessions
Sessions.
-----+-----+-----+-----
Session      | Client      | Service      | State
-----+-----+-----+-----
0x7267a0     | 127.0.0.1   | CLI          | Session ready for routing
0x726340     |              | CLI          | Listener Session
0x725720     |              | Debug Service | Listener Session
0x724720     |              | QLA Service  | Listener Session
0x72a750     |              | Filter Service | Listener Session
0x709500     |              | Split Service | Listener Session
0x7092d0     |              | Test Service  | Listener Session
-----+-----+-----+-----

MaxScale>
```

This lists all the sessions for both user connections and for the service listeners.

The `list clients` command will give just the subset of sessions that originate from a client connection.

```
MaxScale> list clients
Client Connections
-----+-----+-----+-----
Client      | DCB         | Service      | Session
-----+-----+-----+-----
127.0.0.1   | 0x7274b0    | CLI          | 0x727700
127.0.0.1   | 0x727900    | QLA Service  | 0x727da0
-----+-----+-----+-----
```



w: www.mariadb.com

e: info@mariadb.com

```
MaxScale>
```

Display Session Details

Once the session ID has been determined using one of the above method it is possible to determine more detail regarding a session by using the `show session` command.

```
MaxScale> show session 0x727da0
Session 0x727da0
  State:           Session ready for routing
  Service:         QLA Service (0x70d6a0)
  Client DCB:      0x727900
  Client Address:  127.0.0.1
  Connected:       Wed Jun 25 15:27:21 2014
MaxScale>
```




w: www.mariadb.com

e: info@mariadb.com

Descriptor Control Blocks

The Descriptor Control Block or DCB is a very important entity within MaxScale, it represents the state of each connection within MaxScale. A DCB is allocated for every connection from a client, every network listener and every connection to a backend database. Statistics for each of these connections are maintained within these DCB's.

As with session above the DCB's are not named and are therefore referred to by the use of a unique ID, the memory address of the DCB.

Finding DCB's

There are several ways to determine what DCB's are active within a MaxScale server, the most straightforward being the `list dcbs` command.

```
MaxScale> list dcbs
Descriptor Control Blocks
-----+-----+-----+-----+
DCB      | State                                | Service          | Remote
-----+-----+-----+-----+
0x667170 | DCB for listening socket            | Test Service     |
0x71a350 | DCB for listening socket            | Split Service    |
0x724b40 | DCB for listening socket            | Filter Service   |
0x7250d0 | DCB for listening socket            | QLA Service      |
0x725740 | DCB for listening socket            | Debug Service    |
0x726740 | DCB for listening socket            | CLI              |
0x7274b0 | DCB in the polling loop              | CLI              | 127.0.0.1
0x727900 | DCB in the polling loop              | QLA Service      | 127.0.0.1
0x72e880 | DCB in the polling loop              | QLA Service      |
-----+-----+-----+-----+

MaxScale>
```

A MaxScale server that has activity on it will however have many more DCB's than in the example above, making it hard to find the DCB that you require. The DCB ID is also included in a number of other command outputs, depending on the information you have it may be easier to use other methods to locate a particular DCB.



w: www.mariadb.com

e: info@mariadb.com

DCB Of A Client Connection

To find the DCB for a particular client connection it may be best to start with the `list clients` command and then look at each DCB for a particular client address to determine the one of interest.

DCB Details

The details of an individual DCB can be obtained by use of the `show dcb` command

```
MaxScale> show dcb 0x727900
DCB: 0x727900
  DCB state:          DCB in the polling loop
  Connected to:       127.0.0.1
  Owning Session:     0x727da0
  Statistics:
    No. of Reads:          4
    No. of Writes:         3
    No. of Buffered Writes: 0
    No. of Accepts:        0
    No. of High Water Events: 0
    No. of Low Water Events: 0
MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

Working with Filters

Filters allow the request contents and result sets from a database to be modified for a client connection, pipelines of filters can be created between the client connection and MaxScale router modules.

What Filters Are Configured?

Filters are configured in the configuration file for MaxScale, they are given names and may be included in the definition of a service. The `list filters` command can be used to determine which filters are defined.

```
MaxScale> list filters
```

```
Filters
```

Filter	Module	Options
counter	testfilter	
QLA	qlafilter	/tmp/QueryLog
Replicate	tee	
QLA_BLR	qlafilter	/tmp/QueryLog.blr0
regex	regexfilter	
MySQL5.1	regexfilter	
top10	topfilter	

```
MaxScale>
```

Retrieve Details Of A Filter Configuration

The command `show filter` can be used to display information related to a particular filter.

```
MaxScale> show filter QLA
```

```
Filter 0x719460 (QLA)
```

```
Module:      qlafilter
```

```
Options:     /tmp/QueryLog
```

```
Limit logging to connections from      127.0.0.1
```

```
Include queries that match      select.*from.*user.*where
```

```
MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

Filter Usage

The `show session` command will include details for each of the filters in use within a session. First use `list sessions` or `list clients` to find the session of interest and then run the `show session` command

```
MaxScale> list clients
```

```
Client Connections
```

Client	DCB	Service	Session
127.0.0.1	0x7361a0	Split Service	0x736680
127.0.0.1	0x737ec0	Plumbing	0x7382b0
127.0.0.1	0x73ab20	DigitalOcean	0x73ad90
127.0.0.1	0x7219e0	CLI	0x721bd0

```
MaxScale> show session 0x736680
```

```
Session 0x736680
```

```
State: Session ready for routing
```

```
Service: Split Service (0x719f60)
```

```
Client DCB: 0x7361a0
```

```
Client Address: 127.0.0.1
```

```
Connected: Thu Jun 26 10:10:44 2014
```

```
Filter: top10
```

```
Report size 10
```

```
Logging to file /tmp/Query.top10.1.
```

```
Current Top 10:
```

```
1 place:
```

```
Execution time: 23.826 seconds
```

```
SQL: select sum(salary), year(from_date) from salaries s,
(select distinct year(from_date) as y1 from salaries) y where (makedate(y.y1,
1) between s.from_date and s.to_date) group by y.y1 ("1988-08-01?
```

```
2 place:
```

```
Execution time: 5.251 seconds
```

```
SQL: select d.dept_name as "Department", y.y1 as "Year",
count(*) as "Count" from departments d, dept_emp de, (select distinct
year(from_date) as y1 from dept_emp order by 1) y where d.dept_no = de.dept_no
and (makedate(y.y1, 1) between de.from_date and de.to_date) group by y.y1,
d.dept_name order by 1, 2
```

```
3 place:
```

```
Execution time: 2.903 seconds
```

```
SQL: select year(now()) - year(birth_date) as age, gender,
avg(salary) as "Average Salary" from employees e, salaries s where e.emp_no =
s.emp_no and ("1988-08-01" between from_date AND to_date) group by year(now())
- year(birth_date), gender order by 1,2
```



w: www.mariadb.com

e: info@mariadb.com

```
4 place:
    Execution time: 2.138 seconds
    SQL: select dept_name as "Department", sum(salary) / 12 as
"Salary Bill" from employees e, departments d, dept_emp de, salaries s where
e.emp_no = de.emp_no and de.dept_no = d.dept_no and ("1988-08-01" between
de.from_date AND de.to_date) and ("1988-08-01" between s.from_date AND
s.to_date) and s.emp_no = e.emp_no group by dept_name order by 1
5 place:
    Execution time: 0.839 seconds
    SQL: select dept_name as "Department", avg(year(now()) -
year(birth_date)) as "Average Age", gender from employees e, departments d,
dept_emp de where e.emp_no = de.emp_no and de.dept_no = d.dept_no and ("1988-
08-01" between from_date AND to_date) group by dept_name, gender
6 place:
    Execution time: 0.662 seconds
    SQL: select year(hire_date) as "Hired", d.dept_name,
count(*) as "Count" from employees e, departments d, dept_emp de where
de.emp_no = e.emp_no and de.dept_no = d.dept_no group by d.dept_name,
year(hire_date)
7 place:
    Execution time: 0.286 seconds
    SQL: select moves.n_depts As "No. of Departments",
count(moves.emp_no) as "No. of Employees" from (select del.emp_no as emp_no,
count(del.emp_no) as n_depts from dept_emp del group by del.emp_no) as moves
group by moves.n_depts order by 1
8 place:
    Execution time: 0.248 seconds
    SQL: select year(now()) - year(birth_date) as age, gender,
count(*) as "Count" from employees group by year(now()) - year(birth_date),
gender order by 1,2@
9 place:
    Execution time: 0.182 seconds
    SQL: select year(hire_date) as "Hired", count(*) as "Count"
from employees group by year(hire_date)
10 place:
    Execution time: 0.169 seconds
    SQL: select year(hire_date) - year(birth_date) as "Age",
count(*) as Count from employees group by year(hire_date) - year(birth_date)
order by 1

MaxScale>
```

The data displayed varies from filter to filter, the example above is the top filter. This filter prints a report of the current top queries at the time the `show session` command is run.



w: www.mariadb.com

e: info@mariadb.com



w: www.mariadb.com

e: info@mariadb.com

Working With Monitors

Monitors are used to monitor the state of databases within MaxScale in order to supply information to other modules, specifically the routers within MaxScale.

What Monitors Are Running?

To see what monitors are running within MaxScale use the `list monitors` command.

```
MaxScale> list monitors
+-----+-----+
| Monitor                | Status |
+-----+-----+
| MySQL Monitor          | Running |
+-----+-----+
MaxScale>
```

Details Of A Particular Monitor

To see the details of a particular monitor use the `show monitor` command.

```
MaxScale> show monitor "MySQL Monitor"
Monitor: 0x71c370
  Name:      MySQL Monitor
  Monitor running
  Sampling interval: 10000 milliseconds
  MaxScale MonitorId: 24209641
  Replication lag: disabled
  Monitored servers: 127.0.0.1:3306, 127.0.0.1:3307, 127.0.0.1:3308,
127.0.0.1:3309
MaxScale>
```

Controlling Replication Heartbeat

Some monitors provide a replication heartbeat mechanism that monitors the delay for data that is replicated from a master to slaves in a tree structured replication environment. This can be enabled or disabled using the commands `enable heartbeat` and `disable heartbeat`.

```
MaxScale> disable heartbeat "MySQL Monitor"
MaxScale> enable heartbeat "MySQL Monitor"
```



w: www.mariadb.com

e: info@mariadb.com

```
MaxScale>
```

Please note that changes made via this interface will not persist across restarts of MaxScale. To make a permanent change edit the `MaxScale.cnf` file.

Enabling the replication heartbeat mechanism will add the display of heartbeat information in the show server output

```
MaxScale> show server server4
Server 0x719800 (server4)
  Server:                127.0.0.1
  Status:                Slave, Running
  Protocol:              MySQLBackend
  Port:                  3309
  Server Version:        5.5.25-MariaDB-log
  Node Id:               4
  Number of connections: 0
  Current no. of conns:  0
MaxScale> enable heartbeat "MySQL Monitor"
MaxScale> show server server4
Server 0x719800 (server4)
  Server:                127.0.0.1
  Status:                Slave, Running
  Protocol:              MySQLBackend
  Port:                  3309
  Server Version:        5.5.25-MariaDB-log
  Node Id:               4
  Slave delay:           0
  Last Repl Heartbeat:   Thu Jun 26 17:04:58 2014
  Number of connections: 0
  Current no. of conns:  0
MaxScale>
```

Shutting Down A Monitor

A monitor may be shutdown using the `shutdown monitor` command. This allows for manual control of the status of servers using the `set server` and `clear server` commands.

```
MaxScale> shutdown monitor "MySQL Monitor"
MaxScale> list monitors
+-----+-----+
| Monitor                | Status |
+-----+-----+
```




w: www.mariadb.com

e: info@mariadb.com

```
| MySQL Monitor          | Stopped
+-----+-----+
MaxScale>
```

Restarting A Monitor

A monitor that has been shutdown may be restarted using the `restart monitor` command.

```
MaxScale> restart monitor "MySQL Monitor"
MaxScale> show monitor "MySQL Monitor"
Monitor: 0x71a310
      Name:      MySQL Monitor
      Monitor running
      Sampling interval: 10000 milliseconds
      MaxScale MonitorId: 24201552
      Replication lag:   enabled
      Monitored servers: 127.0.0.1:3306, 127.0.0.1:3307, 127.0.0.1:3308,
127.0.0.1:3309
MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

Working With Administration Interface Users

A default installation of MaxScale allows connection to the administration interface using the username of `admin` and the password `skysql`. This username and password stay in effect as long as no other users have been created for the administration interface. As soon as the first user is added the use of `admin/skysql` as login credentials will be disabled.

What Users Have Been Defined?

In order to see the current users that have been defined for the administration interface use the command `show users`.

```
MaxScale> show users
Administration interface users:
Users table data
Hashtable: 0x734470, size 52
    No. of entries:                5
    Average chain length:          0.1
    Longest chain length:          2
User names: vilho, root, dba, massi, mark
MaxScale>
```

Please note that if no users have been configured the default `admin/skysql` user will not be shown.

```
MaxScale> show users
Administration interface users:
No administration users have been defined.
MaxScale>
```

Add A New User

To add a new administrative user to the MaxScale server use the command `add user`. This command is passed a user name and a password.

```
MaxScale> add user maria dtbse243
User maria has been successfully added.
MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

Delete A User

To remove a user the command `remove user` is used, it must also be called with the username and password of the user. The password will be checked.

```
MaxScale> remove user maria des
Failed to remove user maria. Authentication failed
MaxScale> remove user maria dtbse243
User maria has been successfully removed.
MaxScale>
```



w: www.mariadb.com

e: info@mariadb.com

MaxScale Status Commands

A number of commands exists that enable the internal MaxScale status to be revealed, these commands give an insight to how MaxScale is using resource internally and are used to allow the tuning process to take place.

MaxScale Thread Usage

MaxScale uses a number of threads, as defined in the MaxScale configuration file, to execute the processing of requests received from clients and the handling of responses. The `show threads` command can be used to determine what each thread is currently being used for.

```
MaxScale> show threads
Polling Threads.
```

```
Historic Thread Load Average: 1.00.
Current Thread Load Average: 1.00.
15 Minute Average: 0.48, 5 Minute Average: 1.00, 1 Minute Average: 1.00
```

```
Pending event queue length averages:
15 Minute Average: 0.90, 5 Minute Average: 1.83, 1 Minute Average: 2.00
```

ID	State	# fds	Descriptor	Running	Event
0	Processing	1	0xf55a70	< 100ms	IN OUT
1	Processing	1	0xf49ba0	< 100ms	IN OUT
2	Processing	1	0x7f54c0030d00	< 100ms	IN OUT

```
MaxScale>
```

The resultant output returns data as to the average thread utilisation for the past minutes 5 minutes and 15 minutes. It also gives a table, with a row per thread that shows what DCB that thread is currently processing events for, the events it is processing and how long, to the nearest 100ms has been send processing these events.

The Event Queue

At the core of MaxScale is an event driven engine that is processing network events for the network connections between MaxScale and client applications and MaxScale and the backend servers. It is possible to see the event queue using the `show eventq` command. This will show the events currently being executed and those that are queued for execution.

```
MaxScale> show eventq
```



w: www.mariadb.com

e: info@mariadb.com

```
Event Queue.
DCB          | Status      | Processing Events | Pending Events
-----+-----+-----+-----
0x1e22f10    | Processing  | IN|OUT           |
MaxScale>
```

The output of this command gives the DCB's that are currenting in the event queue, the events queued for that DCB, and events that are beign processed for that DCB.

The Housekeeper Tasks

Internally MaxScale has a housekeeper thread that is used to perform periodic tasks, it is possible to use the command `show tasks` to see what tasks are outstanding within the housekeeper.

```
MaxScale> show tasks
Name          | Type      | Frequency | Next Due
-----+-----+-----+-----
Load Average  | Repeated  | 10        | Wed Nov 19 15:10:51 2014
MaxScale>
```

Administration Commands

What Modules Are In use?

In order to determine what modules are in use, and the version and status of those modules the `list modules` command can be used.

```
MaxScale> list modules
Modules.
-----+-----+-----+-----+-----
Module Name   | Module Type | Version  | API   | Status
-----+-----+-----+-----+-----
tee           | Filter      | V1.0.0   | 1.1.0 | Alpha
qlafilter     | Filter      | V1.1.1   | 1.1.0 | Alpha
topfilter     | Filter      | V1.0.1   | 1.1.0 | Alpha
MySQLBackend  | Protocol    | V2.0.0   | 1.0.0 | Alpha
maxscaled     | Protocol    | V1.0.0   | 1.0.0 | Alpha
telnetd       | Protocol    | V1.0.1   | 1.0.0 | Alpha
MySQLClient   | Protocol    | V1.0.0   | 1.0.0 | Alpha
mysqlmon      | Monitor     | V1.2.0   | 1.0.0 | Alpha
readconnroute | Router      | V1.0.2   | 1.0.0 | Alpha
readwritesplit | Router      | V1.0.2   | 1.0.0 | Alpha
debugcli      | Router      | V1.1.1   | 1.0.0 | Alpha
cli           | Router      | V1.0.0   | 1.0.0 | Alpha
```



w: www.mariadb.com

e: info@mariadb.com

-----+-----+-----+-----+-----

```
MaxScale>
```

This command provides important version information for the module. Each module has two versions; the version of the module itself and the version of the module API that it supports. Also included in the output is the status of the module, this may be “In Development”, “Alpha”, “Beta”, “GA” or “Experimental”.

Rotating the log files

MaxScale write a number of log files in the log directory within MaxScale home directory. The default option for these is that the grow continually, it is recommended that periodically the log files are rotated. This will close the current log file and open a new one with a new name. The log file names use a sequence number which is incremented each time the logs are rotated.

It is possible to rotate just a single log file, using the `flush log` command and the name of the log to flush. The names that are recognised by MaxAdmin are error, message, trace or debug.

```
MaxScale> flush log message
MaxScale>
```

The `flush logs` command may be used to rotate all logs with a single command.

```
MaxScale> flush log
MaxScale>
```

Change MaxScale Logging Options

Two commands are provided to change the logging levels within MaxScale, `disable log` and `enable log`. Using these commands the various log levels can be turned on and off, the supported levels are trace, debug and message. The error log level can not be turned off.

```
MaxScale> enable log trace
MaxScale> disable log debug
MaxScale>
```

Please note that changes made via this interface will not persist across restarts of MaxScale. To make a permanent change edit the `MaxScale.cnf` file.

Reloading The Configuration

A command, `reload config`, is available that will cause MaxScale to reload the `MaxScale.cnf` configuration file.



w: www.mariadb.com

e: info@mariadb.com

Shutting Down MaxScale

The MaxScale server may be shutdown using the `shutdown maxscale` command.



w: www.mariadb.com

e: info@mariadb.com

Configuring MaxScale to Accept MaxAdmin Connections

In order to allow the use of the MaxAdmin client interface the service must be added to the MaxScale.cnf file of the Maxscale server. The CLI service itself must be added and a listener for the maxscaled protocol.

The default entries required are shown below.

```
[CLI]
type=service
router=cli

[CLI Listener]
type=listener
service=CLI
protocol=maxscaled
address=localhost
port=6603
```

Note that this uses the default port of 6603 and confines the connections to localhost connections only. Remove the `address=` entry to allow connections from any machine on your network. Changing the port from 6603 will mean that you must allow pass a -p option to the MaxAdmin command.

Tuning MaxScale

The way that MaxScale does its polling is that each of the polling threads, as defined by the `threads` parameter in the configuration file, will call `epoll_wait` to obtain the events that are to be processed. The events are then added to a queue for execution. Any thread can read from this queue, not just the thread that added the event.

Once the thread has done an `epoll` call with no timeout it will either do an `epoll_wait` call with a timeout or it will take an event from the queue if there is one. These two new parameters affect this behaviour.

The first parameter, which may be set by using the `non_blocking_polls` option in the configuration file, controls the number of `epoll_wait` calls that will be issued without a timeout before MaxScale will make a call with a timeout value. The advantage of performing a call without a timeout is that the kernel treats this case as different and will not rescheduled the



w: www.mariadb.com

e: info@mariadb.com

process in this case. If a timeout is passed then the system call will cause the MaxScale thread to be put back in the scheduling queue and may result in lost CPU time to MaxScale. Setting the value of this parameter too high will cause MaxScale to consume a lot of CPU when there is infrequent work to be done. The default value of this parameter is 3.

This parameter may also be set via the maxadmin client using the command `set nbpolls <number>`.

The second parameter is the maximum sleep value that MaxScale will pass to `epoll_wait`. What normally happens is that MaxScale will do an `epoll_wait` call with a sleep value that is 10% of the maximum, each time the returns and there is no more work to be done MaxScale will increase this percentage by 10%. This will continue until the maximum value is reached or until there is some work to be done. Once the thread finds some work to be done it will reset the sleep time it uses to 10% of the maximum.

The maximum sleep time is set in milliseconds and can be placed in the [maxscale] section of the configuration file with the `poll_sleep` parameter. Alternatively it may be set in the maxadmin client using the command `set pollsleep <number>`. The default value of this parameter is 1000.

Setting this value too high means that if a thread collects a large number of events and adds to the event queue, the other threads might not return from the `epoll_wait` calls they are running for some time resulting in less overall performance. Setting the sleep time too low will cause MaxScale to wake up too often and consume CPU time when there is no work to be done.

The `show epoll` command can be used to see how often we actually poll with a timeout, the first two values output are significant. Also the “Number of wake with pending events” is a good measure. This is the count of the number of times a blocking call returned to find there was some work waiting from another thread. If the value is increasing rapidly reducing the maximum sleep value and increasing the number of non-blocking polls should help the situation.

```
MaxScale> show epoll
Number of epoll cycles:          534
Number of epoll cycles with wait: 10447
Number of read events:          35
Number of write events:         1988
Number of error events:         0
Number of hangup events:        1
```



w: www.mariadb.com

e: info@mariadb.com

```
Number of accept events:          3
Number of times no threads polling: 5
Current event queue length:       1
Maximum event queue length:       2
Number of DCBs with pending events: 0
Number of wakeups with pending queue: 0
No of poll completions with descriptors
      No. of descriptors      No. of poll completions.
      1                      534
      2                      0
      3                      0
      4                      0
      5                      0
      6                      0
      7                      0
      8                      0
      9                      0
     >= 10                   0
MaxScale>
```

If the “Number of DCBs with pending events” grows rapidly it is an indication that MaxScale needs more threads to be able to keep up with the load it is under.

The `show threads` command can be used to see the historic average for the pending events queue, it gives 15 minute, 5 minute and 1 minute averages. The load average it displays is the event count per poll cycle data. An idea load is 1, in this case MaxScale threads and fully occupied but nothing is waiting for threads to become available for processing.

The `show eventstats` command can be used to see statistics about how long events have been queued before processing takes place and also how long the events took to execute once they have been allocated a thread to run on.

```
MaxScale> show eventstats
```

```
Event statistics.
Maximum queue time:          2600ms
Maximum execution time:      1600ms
Maximum event queue length:   3
Current event queue length:   3
```



w: www.mariadb.com

e: info@mariadb.com

Duration	Number of events	
	Queued	Executed
-----+-----+-----		
< 100ms	107	461
100 - 200ms	958	22830
200 - 300ms	20716	2545
300 - 400ms	3284	253
400 - 500ms	505	45
500 - 600ms	66	73
600 - 700ms	116	169
700 - 800ms	319	185
800 - 900ms	382	42
900 - 1000ms	95	31
1000 - 1100ms	63	7
1100 - 1200ms	18	4
1200 - 1300ms	8	2
1300 - 1400ms	6	0
1400 - 1500ms	1	1
1500 - 1600ms	3	1
1600 - 1700ms	2	1
1700 - 1800ms	2	0
1800 - 1900ms	0	0
1900 - 2000ms	1	0
2000 - 2100ms	0	0
2100 - 2200ms	0	0
2200 - 2300ms	0	0
2300 - 2400ms	0	0
2400 - 2500ms	0	0
2500 - 2600ms	0	0
2600 - 2700ms	1	0
2700 - 2800ms	0	0
2800 - 2900ms	0	0
2900 - 3000ms	0	0
> 3000ms	0	0
MaxScale>		

The statics are defined in 100ms buckets, with the count of the events that fell into that bucket being recorded.